WORLD JOURNAL OF PHARMACEUTICAL RESEARCH
Coden USA: WJPRAP Impact Factor 8.63
Volume 15, Issue 21, 794-816. Review Article ISSN 2277–7105

A COMPREHENSIVE REVIEW OF CONTAMINATION, ANALYTICAL TECHNIQUES, QUALITY CONTROL AND SAFETY

Saira Bhanu Shaik[*1], A. Varalakshmi[2], G. Akhila Bhanu Prasana[3], M. A. V. D. S. Prajna[4], M. Vamsi Vara Prasad[5], P. Sai Srinu[6], G. Ch. Janush[7], Ch. Siva Durga[8]

[1]Assistant Professor, M. Pharm; (Ph.D), Dept. of Pharmaceutical Analysis, Koringa College of Pharmacy, Korangi, Kakinada, Andhra Pradesh, India.

[2-8]B.Pharm Scholar, Department of Pharmacy Practice, Koringa College of Pharmacy, Korangi, Kakinada, Andhra Pradesh, India.

Article Received on 05 Oct. 2026,
Article Revised on 25 Oct. 2026,
Article Published on 01 Nov. 2026,

https://doi.org/10.5281/zenodo.23763986

***Corresponding Author**
Saira Bhanu Shaik

Assistant Professor, M. Pharm; (Ph.D), Dept. of Pharmaceutical Analysis, Koringa College of Pharmacy, Korangi, Kakinada, Andhra Pradesh, India.

How to cite this Article: Saira Bhanu Shaik[*1], M. Vamsi Vara Prasad[2], M. A. V. D. S. Prajna[3], P. Sai Srinu[4], A. Vara Lakshmi[5], Ch. Siva Durga[6], G. Akhila Bhanu Prasanna[7], Ch. Janush[8] (2026). A Comprehensive Review Of Contamination, Analytical Techniques, Quality Control And Safety. World Journal of Pharmaceutical Research, 15(21), 794–816.
This work is licensed under Creative Commons Attribution 4.0 International license.

ABSTRACT

Herbal drug formulations are increasingly used as traditional, complementary and supportive healthcare products. Although their botanical origin is often associated with natural safety, medicinal plants can accumulate potentially toxic elements from soil, irrigation water, atmospheric deposition, agricultural inputs and contaminated processing environments. Lead, cadmium, mercury and arsenic are among the most important contaminants because repeated exposure can produce neurological, renal, cardiovascular, hematological and other systemic effects. Consequently, determination of elemental contaminants is an essential part of the quality assessment of herbal medicines. This review presents an integrated discussion of the occurrence and significance of toxic elements in herbal drug formulations, environmental and manufacturing sources of contamination, plant uptake and translocation, sampling, homogenization and digestion, conventional limit tests, atomic absorption spectrometry, inductively coupled plasma optical emission spectrometry, inductively coupled plasma mass spectrometry, X-ray fluorescence and electrochemical approaches. It further discusses method validation, quality-control samples, calibration, blanks, recovery, detection limits, uncertainty and regulatory interpretation. A reliable

analytical strategy begins with representative sampling and suitable sample preparation and ends with a scientifically justified interpretation of the measured concentration. Modern multi-element techniques provide sensitive and efficient analysis, but their performance depends on matrix control, contamination prevention and appropriate validation. Risk-based control across cultivation, procurement, processing and finished-product testing provides stronger consumer protection than reliance on a single end-product test.

KEYWORDS: Herbal drugs; heavy metals; toxic elements; lead; cadmium; mercury; arsenic; AAS; ICP-OES; ICP-MS; XRF; elemental impurities; quality control; method validation; risk assessment.

1. INTRODUCTION: Herbal Medicines and the Hidden Burden of Elemental Contamination

Herbal medicines are prepared from whole plants, plant parts, extracts, essential oils and combinations of botanicals. They are marketed as powders, capsules, tablets, teas, decoctions, syrups, tinctures and concentrated extracts. Their chemical composition is naturally complex and may vary according to species, geographical origin, soil characteristics, climate, cultivation practice, harvesting season and processing. Such variability is an important quality-control consideration because the elemental composition of the raw material can also vary.[1]

Plants require several mineral elements for normal growth, including iron, zinc, copper, manganese and molybdenum. However, non-essential elements such as lead and cadmium can also enter plant tissues. Arsenic and mercury may occur in environmental compartments and can become relevant contaminants depending on the source and processing history. Therefore, elemental analysis should distinguish essential nutritional elements from toxic contaminants and should be designed according to the risk profile of the product.[2]


The phrase heavy metals is widely used in quality-control literature, although the scientific definition is not completely uniform. In analytical practice, the more precise expression potentially toxic elements is often preferable because arsenic is a metalloid and because toxicological behavior depends on chemical species rather than density alone. Nevertheless, heavy-metal testing remains a familiar regulatory and pharmaceutical term.[3]

Medicinal plants can act as bioaccumulators. Their roots interact directly with soil, while leaves and aerial parts may receive atmospheric particles. Water used for irrigation or washing can introduce additional contaminants. During drying, grinding and extraction, contamination can also arise from equipment, water, reagents and storage surfaces. A finished formulation may therefore contain an elemental profile that differs from that of the original plant material.[4]

International quality-control guidance emphasizes that medicinal plant materials must be evaluated for contaminants and residues as part of an overall quality system. Determination of heavy metals is not an isolated analytical exercise; it is one element of a broader system involving botanical identity, cultivation control, processing hygiene, specifications and documented release decisions.[4]

Analytical measurement becomes particularly important when a product is consumed repeatedly. Even a relatively low concentration can contribute to cumulative exposure when the daily dose is large or treatment continues for months. Risk assessment should therefore combine the measured concentration with the amount of product consumed and the duration of exposure rather than relying solely on concentration values.[5]

The objective of this review is to provide a structured overview of the determination of toxic elements in herbal drug formulations, from the origin of contamination to modern instrumental analysis. Emphasis is placed on practical analytical considerations so that the laboratory result can be interpreted as reliable evidence of product quality and safety.



2. Why Heavy Metals Matter in Herbal Drug Formulations

Heavy metals are important toxicological contaminants because several of them persist in the environment and can remain in biological systems for prolonged periods. Lead, cadmium, mercury and inorganic arsenic can interfere with cellular processes, enzymes, membrane function, oxidative balance and tissue physiology. The severity of effects depends on dose, chemical form, route of exposure and duration.[6]

Lead is particularly important because there is no established physiological requirement for human exposure to lead. Chronic exposure can affect neurodevelopment, blood formation, kidney function and cardiovascular health. Children are especially vulnerable to neurotoxic effects, while adults can also experience significant consequences from prolonged exposure.[7]

Cadmium is associated with accumulation in the kidney and with chronic renal toxicity. Long-term exposure can also affect bone mineralization and skeletal health. The long biological persistence of cadmium means that repeated low-level exposure may be more important than a single short exposure.[8]


Mercury toxicity is strongly influenced by chemical form. Elemental mercury, inorganic mercury compounds and organic mercury compounds differ in absorption, distribution and target-organ effects. This is why total mercury measurement and mercury speciation answer different analytical questions.[9]

Arsenic is similarly species-dependent. Inorganic arsenic is a major toxicological concern, whereas organic arsenic compounds found in some foods may have different toxicity. For herbal medicines, the analytical approach should therefore reflect the toxicological question and the form in which arsenic is expected to occur.[10]

The presence of an element does not automatically mean that a product is unsafe. Safety assessment requires consideration of concentration, daily dose, exposure duration and applicable limits. A laboratory report should therefore present the analytical result with units, basis of calculation, uncertainty where relevant and a clear comparison with the appropriate specification.[11]

Heavy-metal control is also important for public confidence in herbal medicines. Consistent testing, traceable raw materials and transparent quality specifications can reduce the

possibility that contaminated products reach consumers and can support the responsible integration of herbal products into modern healthcare systems.



3. Major Toxic Elements: Lead, Cadmium, Mercury and Arsenic

Lead is commonly considered one of the most important elemental contaminants in herbal medicines. It can enter plants from contaminated soil, irrigation water, atmospheric deposition, dust and industrial emissions. Post-harvest contamination may arise from equipment, pigments, storage materials or environmental dust. Because lead can occur at trace concentrations, sensitive instrumental methods are often required for reliable determination.[12]

Cadmium can be taken up from soil through plant transport processes associated with essential nutrients. Its accumulation varies among plant species and plant organs. Root materials may be particularly relevant because they are in direct contact with soil, although translocation to aerial tissues can also occur.[12]

Mercury requires special analytical attention because of its volatility and chemical diversity. Sample preparation conditions should minimize losses, and laboratories should select a technique capable of providing adequate sensitivity at the expected concentration. Cold-vapor atomic absorption and ICP-MS are examples of approaches used for mercury determination.[12]

Arsenic can occur in inorganic and organic forms. Hydride-generation methods, atomic fluorescence and ICP-MS can be used when low concentrations or enhanced selectivity are

required. Total arsenic determination is adequate for many screening applications, whereas speciation becomes important when the toxicological significance of individual species must be assessed.[12]

Chromium, nickel and other elements may also be relevant depending on the raw material, environmental source and manufacturing equipment. Chromium illustrates the importance of chemical form because trivalent and hexavalent chromium have very different toxicological properties. A risk-based laboratory program should therefore identify the elements that are plausible contaminants rather than applying an identical panel to every product.[13]

Essential elements such as iron, zinc, copper and manganese may be naturally present or intentionally introduced. Their measurement can support nutritional characterization and help identify unusual batches. However, the analytical method must differentiate expected formulation levels from toxic contamination and must use suitable acceptance criteria.[12]

An elemental profile can therefore provide information about both safety and product consistency. Unexpected increases in one or more elements may trigger investigation of a supplier, cultivation area, processing step or packaging component. Trend monitoring can sometimes detect emerging problems before a formal specification is exceeded.




Table 1: Principal toxic elements and analytical considerations.

Elements	Major toxicological concern	Likely sources	Common methods
Lead [pb]	Neurological and hematological effects	Soil, dust, water, processing	AAS,ICP-OES, ICP-MS XRF
Cadmium [cd]	Renal and skeletal effects	Soil, fertilizers, irrigation	AAS, ICP-OES, ICP-MS
Mercury [Hg]	Neurological / systemic effects	Environmental and process sources	CV-AAS, AAS, ICP-MS
Arsenic [As]	Systemic toxicity, inorganic species	Soil, water, environmental sources	Hydride methods, AAS, ICP-MS
Chromium [cr]	Form-dependent toxicity	Soil, equipment, environment	AAS, ICP-OES, ICP-MS
Nickel [Ni]	Sensitization and systemic effects	Soil , equipment, environment	AAS,ICP-OES, ICP-MS

4. Natural and Anthropogenic Sources of Metal Contamination

Environmental contamination is one of the earliest possible sources of toxic elements in medicinal plants. Geological parent material can naturally contain arsenic, lead, cadmium or other elements. In addition, mining, smelting, industrial emissions, traffic, waste disposal and contaminated agricultural land can increase environmental concentrations.[14]

Soil chemistry controls the availability of elements to plants. Factors such as pH, organic matter, redox potential, clay content and cation-exchange capacity influence whether an element remains strongly bound to soil or becomes available for root uptake. Thus, total soil concentration does not always predict the concentration that will occur in plant tissue.[14]


Irrigation water can act as an important pathway. Contaminated surface water, groundwater or wastewater used for cultivation can deposit elements in soil and directly expose plant tissues. Water used during washing and extraction can also introduce contaminants into the manufacturing process if its quality is not controlled.[14]

Agricultural inputs may contribute to elemental contamination. Certain fertilizers, soil amendments and pesticides can contain trace metals as impurities. Repeated application can gradually increase soil burdens. Good agricultural and collection practices therefore need to include appropriate site selection, water quality assessment and control of agricultural inputs.[14]

Airborne particles provide another pathway. Leaves and other aerial organs can collect dust containing metals, especially in areas affected by traffic or industrial activity. Washing may remove some surface particles, but it cannot reliably remove elements that have been absorbed into internal tissues.[14]

Manufacturing equipment can also be a source. Grinding surfaces, metallic vessels, pipes and extraction equipment may release trace elements if they are corroded or unsuitable. Contact materials should therefore be selected according to the formulation and analytical risk profile.[14]

Packaging and storage conditions deserve attention when contamination is unexplained by the raw material. Containers, closures, pigments, printing materials and environmental dust can contribute contaminants. A complete investigation should therefore examine the whole product pathway rather than assuming that every metal originates in the plant.



5. Plant Uptake, Accumulation and Translocation of Toxic Elements

Plant uptake begins at the interface between roots and the surrounding soil solution. Dissolved ions can enter root tissues through transport pathways that normally handle essential nutrients. Because toxic elements can resemble or compete with essential ions, changes in nutrient status and soil chemistry can alter uptake.[12]

Cadmium provides a clear example of non-essential element uptake through nutrient-related transport systems. Once inside the plant, it can bind to peptides and proteins or be transported to aerial tissues. Plants differ considerably in their capacity to retain or translocate cadmium.[12]


Lead often shows strong retention in roots, although some translocation can occur. Surface deposition may also contribute to the measured concentration of leaves. Distinguishing absorbed from surface-associated material is difficult in routine analysis, which is why standardized sample preparation and washing procedures are important.[15]

Arsenic interacts with phosphate-related pathways and may therefore show uptake patterns influenced by phosphate availability. The chemical species of arsenic strongly influences transport and metabolism. These mechanisms illustrate why total environmental concentration alone cannot explain the final concentration in a medicinal plant.[12]

Mercury can bind strongly to sulfur-containing biomolecules and may be retained in roots or translocated depending on the chemical environment. Volatile species can behave differently from inorganic forms. These characteristics should be considered when designing analytical procedures and interpreting unusual results.[12]

Plant organ selection is also important. Root, rhizome, bark, leaf, flower, fruit and seed materials may have different elemental profiles. A specification developed for a leaf preparation should not automatically be applied to a root preparation without considering the different exposure and accumulation patterns.[12]

Preventive strategies include selecting uncontaminated cultivation sites, testing soil and water, controlling agricultural inputs and monitoring harvested material. These measures reduce reliance on end-product testing and help establish a traceable chain of control from cultivation to finished formulation.[12]



6. From Raw Botanical Material to Finished Formulation: Critical Contamination Points

Quality control should begin with identification and qualification of the botanical raw material. Correct species identification, plant part specification and supplier traceability are essential because elemental profiles can vary among species, locations and plant organs. A chemically or botanically misidentified material can invalidate later analytical conclusions.[1]

Sampling at the raw-material stage should be representative of the batch. Heterogeneous botanical materials may contain localized mineral particles or dust, so a single small grab sample may not represent the entire lot. Sampling plans should define locations, quantities, pooling strategy and storage conditions.[16]


Drying can alter elemental concentrations on a wet-weight basis because removal of water increases the concentration per unit mass. Therefore, moisture content and reporting basis must be recorded. A laboratory should state whether results are expressed on an as-received, dry-weight or another validated basis.[4]

Grinding and sieving improve homogeneity but can introduce contamination. Equipment should be cleaned between samples, and materials of construction should be compatible with the target analytes. Where trace concentrations are measured, laboratory contamination can become comparable with the amount present in the sample.[3]

Extraction and concentration steps may change the apparent elemental concentration. Elements associated with insoluble particles may be incompletely transferred into an extract, while concentration processes can enrich soluble elements. A method intended for total elemental content should therefore use a digestion procedure capable of releasing the analytes quantitatively.[17]

Excipients add another matrix component to finished formulations. Diluents, binders, colors and mineral ingredients can affect digestion and instrumental response. Validation must therefore be performed in representative product matrices rather than only in simple aqueous standards.[18]

An effective manufacturing control system combines supplier qualification, incoming raw-material testing, in-process controls, water quality, equipment monitoring and finished-product testing. Analytical results are most useful when linked to documented corrective actions and trend analysis.



7. Sampling, Digestion and Sample Preparation for Elemental Analysis

Representative sampling is the foundation of reliable elemental analysis. The analytical portion should reflect the batch rather than a convenient portion of the container. Sampling tools should be clean and chemically compatible with the analytes. Documentation should preserve traceability from the batch to the final analytical result.[4]

Homogenization reduces variability by distributing particles throughout the test material. Drying conditions should be controlled because overheating may alter some volatile constituents and because moisture affects the reported concentration. For mercury in particular, sample handling should minimize potential losses.[4]

Open-vessel acid digestion is a traditional approach in which the organic matrix is decomposed using concentrated mineral acids under controlled heating. It can be effective but may require longer processing and can introduce contamination or analyte loss if not carefully controlled.[4]

Microwave-assisted closed-vessel digestion provides controlled temperature and pressure and can improve decomposition of complex plant matrices. Nitric acid is commonly used, with hydrogen peroxide or other reagents included when validated. The digestion program should be optimized for the actual matrix and target elements.[19]

After digestion, the solution may be diluted to bring concentrations into the calibration range. Filtration can remove remaining particles, but filtration materials should be checked for elemental contamination or adsorption. Internal standards and matrix matching can help compensate for instrumental variation.[17]

Blanks are essential. A reagent blank measures contamination introduced by acids, water and vessels, while a preparation blank can reveal contamination from the entire digestion procedure. Duplicate samples, spiked samples and certified reference materials provide additional evidence of method performance.[18]

A practical workflow is representative sampling → homogenization → moisture determination → digestion → dilution → blank correction → calibration → measurement → QC verification → calculation → comparison with specification. Every step should be described in a standard operating procedure and controlled under the laboratory quality system.

8. Classical Approaches: Limit Tests and Colorimetric Procedures

Classical limit tests were developed when instrumental spectrometry was not widely available. Their objective is generally to establish whether the amount of a contaminant is below a specified limit rather than to produce a detailed multi-element profile. They remain historically important and may still be useful in laboratories with limited instrumentation.[4]

Colorimetric methods depend on chemical reactions that produce a measurable or visually comparable color. Their simplicity and low equipment requirement are advantages. However, color intensity can be affected by matrix components, reagent quality, reaction time and analyst interpretation.[3]

Classical tests for arsenic and heavy metals have been incorporated into pharmacopoeial and WHO procedures. These methods demonstrate the principle of comparing a sample response with a reference under controlled conditions. For trace-level release testing, however, modern instrumental methods usually provide greater sensitivity and specificity.[4]

The major limitation of a visual limit test is that it may not provide an accurate concentration. It also provides limited information about which individual elements are responsible for the response when a combined heavy-metal test is used. This can complicate risk assessment and troubleshooting.[3]

Classical procedures may still be appropriate as preliminary screening tools, educational procedures or contingency methods. Their suitability should be demonstrated against the intended specification. If the required limit is close to the method detection capability, a more sensitive instrumental method should be selected.[18]

Whatever method is chosen, contamination control remains critical. Clean glassware, high-purity reagents, suitable water and appropriate blanks are needed. A simple method performed under poor contamination control can produce less reliable results than a sophisticated method operated within a rigorous quality system.

The transition from classical tests to instrumental analysis reflects the broader development of pharmaceutical quality control. Modern methods do not eliminate the need for sound sampling and preparation; rather, they make the consequences of poor preparation more visible because their sensitivity is much higher.

9. Atomic Absorption Spectrometry: A Practical Quantitative Workhorse


Atomic absorption spectrometry measures the absorption of element-specific radiation by free atoms. Because each element has characteristic absorption lines, AAS can provide selective quantitative determination. Flame AAS is generally appropriate for higher concentrations, whereas graphite furnace AAS offers improved ssensitivity for many elements.[20]

AAS is widely used because the instrumentation is established, methods are available for common contaminants and the technique can provide reliable quantitative results. It is particularly practical when a laboratory routinely analyzes a limited group of elements such as lead, cadmium or copper.[20]

Graphite furnace AAS can measure very low concentrations using a small sample volume. The furnace program controls drying, ashing and atomization. Matrix modifiers may be used to stabilize analytes and reduce interference. Background correction is essential when the sample matrix absorbs or scatters radiation at the analytical wavelength.[20]

Specialized AAS configurations can improve the analysis of mercury and arsenic. Cold-vapor techniques are widely used for mercury because the element can be converted to a volatile atomic form. Hydride-generation approaches can improve sensitivity for hydride-forming elements such as arsenic.[21]

Calibration standards should be prepared from traceable stock solutions and should cover the intended concentration range. A reagent blank and independent calibration verification should be included. When matrix effects are substantial, standard addition or mvatrix matching may be necessary.[18]



Validation should demonstrate specificity, linearity, range, accuracy, precision, detection limit, quantification limit and robustness. Recovery experiments in representative herbal matrices are particularly useful because digestion and matrix components can influence the measured response.[22]

AAS remains a strong choice for targeted routine testing. Its main limitation is that sequential measurement of many elements can be slower than simultaneous multi-element techniques. The decision should therefore depend on the laboratory's testing volume, required element panel, sensitivity and available resources.

10. ICP-OES and ICP-MS: Multi-Element Analysis at Modern Sensitivity

ICP-OES uses a high-temperature argon plasma to excite atoms and ions. The emitted radiation is measured at characteristic wavelengths, allowing multiple elements to be determined from one sample. This makes ICP-OES efficient for laboratories that need broad elemental coverage.[23]

ICP-MS introduces ions from the plasma into a mass spectrometer and separates them according to mass-to-charge ratio. It provides very low detection limits and can measure many elements simultaneously. This is particularly useful when herbal formulations contain toxic elements at trace or ultra-trace concentrations.[24]

ICP-OES is generally robust over a broad concentration range and can tolerate many complex matrices after suitable dilution. Spectral overlaps are managed through wavelength selection, background correction and appropriate instrument software. Internal standards can compensate for signal drift and some matrix effects.[23]

ICP-MS offers exceptional sensitivity but requires more careful interference control. Polyatomic ions can overlap with analyte masses. Collision or reaction cell technologies, isotope selection, mathematical correction and appropriate sample dilution can reduce these effects.[24]

Sample digestion remains central to both techniques. Incomplete digestion can produce low results, while contaminated reagents can produce high results. Microwave digestion using high-purity acids is widely used for complex botanical samples. The method should be verified using spikes or certified reference materials.[19]

ICP-based methods are particularly useful for elemental fingerprinting. A single analysis can provide toxic elements together with essential and trace elements. Multivariate analysis of these profiles can support supplier comparison, geographical discrimination and investigation of unusual batches, although such applications should not replace formal quantitative specifications.[25]

The principal disadvantages are capital cost, maintenance requirements, argon consumption and the need for trained analysts. Nevertheless, for laboratories with high sample throughput or broad elemental testing requirements, ICP-OES and ICP-MS can substantially improve analytical efficiency.




Table 2: Comparison of principal analytical techniques.

Technique	**Strength**	**Limitation**	Typical **use**
AAS	Established and reliable	Usually targeted/sequential	Routine targeted metals
ICP-OES	Broad multi-elements range	Spectral/matrix effects	Routine multi-elements QC
ICP-MS	Very high sensitivity	Cost and interference control	Trace/ultra-trace analysis
XRF	Rapid ,little preparation	Matrix detection limitations	Screening of solids
Electrochemical	Potentially portable	Selectivity/fouling	Selected – metal screening

11. XRF, Electrochemical and Emerging Analytical Technologies

X-ray fluorescence is a non-destructive or minimally destructive approach that can analyze many solid samples with little preparation. It measures characteristic fluorescent X-rays emitted after excitation. Benchtop and portable instruments can be useful for rapid screening of botanical powders and raw materials. [26]

The major attraction of XRF is speed. Because complete acid digestion may not be necessary, many samples can be screened quickly. However, performance depends on element, matrix, sample homogeneity and instrument configuration. Detection limits may be higher than those of ICP-MS for certain elements.[26]

Electrochemical techniques such as anodic stripping voltammetry can provide sensitive determination of selected metals. The analyte is accumulated at an electrode and

subsequently stripped while the resulting current is measured. These methods can be relatively inexpensive and potentially portable.[27]

Electrode fouling, matrix effects and selectivity are important limitations. Herbal extracts contain many organic compounds that can influence electrode surfaces. Pretreatment, masking agents and optimized electrode materials may be required.[27]

Laser-ablation ICP-MS can provide spatial information by analyzing material directly from a solid surface. It can help investigate whether an element is localized in particular tissues or particles. Such information may be useful in research on plant uptake and contamination mechanisms.[24]

Hyphenated techniques such as chromatography coupled to ICP-MS can separate elemental species before detection. This is valuable when total concentration alone is insufficient, particularly for arsenic and mercury where chemical species can have very different toxicological properties.[9]

A practical future strategy may use rapid XRF or electrochemical screening for large numbers of samples followed by confirmatory ICP-OES, ICP-MS or AAS analysis. Such tiered testing can improve efficiency while retaining high-quality quantitative confirmation.

12. Method Validation and Laboratory Quality Assurance

Method validation demonstrates that an analytical procedure is fit for its intended purpose. For elemental analysis, the validation design should reflect the concentration range around the specification and the complexity of the herbal matrix. The main characteristics include specificity, accuracy, precision, linearity, range, detection limit, quantification limit and robustness.[22]

Accuracy can be assessed using certified reference materials, reference methods or recovery studies. Certified materials are especially valuable because the assigned concentration is independently characterized. Where appropriate reference materials are unavailable, spiking a representative sample can provide useful evidence of recovery.[18]

Precision includes repeatability under the same conditions and intermediate precision across days, analysts or equipment where relevant. Results should be reported with appropriate significant figures and should not imply greater precision than the method supports.[22]

Detection and quantification limits are particularly important when specifications are low. A method may be technically capable of detecting an element but not of quantifying it with acceptable accuracy at the regulatory limit. The reporting approach should therefore distinguish detected, quantified and below-quantification-limit results.[22]

Linearity should be demonstrated across the working range. Calibration should be verified with independent standards, and continuing calibration checks should be used during long analytical sequences. Drift can otherwise cause systematic errors across a batch of samples.[18]

Robustness assesses the effect of small deliberate changes in conditions. For digestion, this may include acid concentration, digestion time or temperature. For instrumental methods, relevant factors may include plasma conditions, wavelength or gas flow. Robust methods reduce dependence on exact operating conditions.[22]

Quality assurance also includes instrument maintenance, reagent qualification, reference-standard traceability, environmental monitoring, analyst training and controlled documentation. A valid method used in an uncontrolled laboratory can still produce unreliable results.[18]

13. Regulatory Standards, Risk Assessment and Consumer Safety

Regulatory control of elemental contaminants aims to ensure that exposure from medicinal products remains within scientifically acceptable limits. WHO guidance on medicinal plant materials includes quality-control procedures for heavy metals and arsenic, while broader herbal-medicine guidance emphasizes control of contaminants and residues.[4]

Elemental limits should be selected according to the applicable regulatory framework and the nature of the product. Dose, route, duration and intended population can influence the relevance of a concentration limit. Therefore, a limit developed for one product category should not automatically be transferred to another without justification.[5]

ICH Q3D provides a risk-based framework for elemental impurities in pharmaceutical products and establishes permitted daily exposures for specified elements. However, its formal scope does not cover herbal products. Herbal-medicine manufacturers should therefore follow the applicable national or regional requirements while using scientifically sound risk-management principles.[28]

Exposure can be estimated from the concentration measured and the daily amount consumed. A simplified relationship is: estimated daily exposure = elemental concentration × daily product intake. More detailed assessments may include absorption, bioaccessibility, frequency of use and exposure from other sources.[5]

Risk assessment should also consider vulnerable groups, including children, pregnant individuals and people with kidney or other susceptibility factors. The purpose is not to assume that every detected element causes harm, but to determine whether realistic exposure could approach a level of toxicological concern.[6]

Supplier qualification is an important preventive measure. Contracts and specifications can require information on cultivation site, water source, agricultural practices and contamination controls. Periodic testing can verify supplier performance and detect changes in elemental profiles over time.[14]

Trend analysis strengthens the quality system. A result can be below the specification yet still represent a meaningful increase compared with previous batches. Alert levels, investigation triggers and corrective-action procedures can help identify contamination before it becomes a major quality failure.

14. Future Perspectives: Toward Rapid, Green and Data-Driven Metal Analysis

Future elemental analysis will increasingly combine high sensitivity with rapid sample throughput. ICP-MS and ICP-OES will remain important laboratory platforms, while portable XRF and electrochemical systems may support field screening and raw-material triage. The optimal strategy is likely to be a combination of complementary technologies rather than dependence on one instrument.[24]

Green analytical chemistry provides another direction. Traditional digestion can require concentrated acids and generate chemical waste. Closed-vessel microwave digestion, miniaturized procedures, reduced sample masses and optimized reagent volumes can lower environmental burden while maintaining analytical performance.[29]


Automation can reduce manual errors in weighing, digestion, dilution and data transfer. Automated sample introduction and laboratory information-management systems can improve traceability. However, automation should be validated and controlled just like any other analytical process.

Data analytics can provide additional value from elemental measurements. Multivariate statistical approaches can identify patterns associated with suppliers, geographical origins, processing steps or unusual batches. These tools can support investigation and surveillance, but final release decisions should remain based on validated quantitative methods and approved specifications.[25]

Speciation is likely to become more important when toxicological interpretation depends on chemical form. Total arsenic or mercury may be sufficient for screening, whereas chromatography coupled with elemental detection can provide species-specific information when needed.[9]

Future research should also examine bioaccessibility rather than concentration alone. An element present in a plant matrix may not be completely released during human digestion. Simulated gastrointestinal extraction and other Bioaccessibility approaches can therefore complement total elemental analysis in research-oriented risk assessment.

The central future objective is preventive quality assurance: selecting safe cultivation sites, controlling agricultural inputs, monitoring raw materials, validating processing, testing finished products and using trend data to detect emerging risks. Such a system transforms heavy-metal analysis from a final inspection step into an integrated safety.



CONCLUSION

The determination of heavy metals in herbal drug formulations is an essential component of pharmaceutical quality control and consumer safety. Herbal medicines may become contaminated with toxic elements such as lead, cadmium, mercury and arsenic through soil, irrigation water, atmospheric deposition, agricultural inputs, processing equipment, packaging and storage conditions. Therefore, the safety of herbal formulations cannot be assured only by their natural or botanical origin. Reliable determination depends on every stage of the analytical process, beginning with representative sampling, proper homogenization and suitable digestion, followed by accurate instrumental analysis. Classical limit tests may provide preliminary screening, whereas modern techniques such as AAS, ICP-OES and ICP-MS offer sensitive and quantitative determination of toxic elements. XRF and electrochemical techniques can also support rapid or selected-metal screening. However, the reliability of any analytical technique depends on proper contamination control, calibration, method validation, quality-control samples and appropriate interpretation of results. A risk-based quality-control system should extend from cultivation and selection of botanical raw materials to processing and finished-product testing. Supplier qualification, monitoring of soil and water, control of agricultural inputs, hygienic processing, suitable equipment, validated analytical procedures and trend analysis can reduce the possibility of contaminated products reaching consumers. Future developments in rapid screening, green analytical chemistry, automation, elemental speciation and data-driven analysis may further improve the efficiency and reliability of heavy-metal determination. Overall, heavy-metal analysis should not be considered merely as a final testing step but as an integrated part of herbal-drug quality assurance. Combining preventive measures with validated analytical methods and scientifically justified risk assessment can help ensure the quality, consistency and safety of herbal drug formulations and strengthen consumer confidence in their use.

REFERENCES

1. Naozuka J, de Oliveira AP, de Oliveira HB, de Oliveira Lima L, Nomura CS. Determination of Essential and Toxic Elements by ICP-MS in Herbal Medicines. ACS Omega, 2025. doi:10.1021/acsomega.5c05971.
2. Welz B, Sperling M. Atomic Absorption Spectrometry. 3rd ed. Weinheim: Wiley-VCH, 1999.
3. World Health Organization. WHO Guidelines for Assessing Quality of Herbal Medicines with Reference to Contaminants and Residues. Geneva: WHO, 2007.

4. World Health Organization. Quality Control Methods for Herbal Materials. Geneva: WHO, 2011.
5. International Council for Harmonisation. ICH Q3D(R2): Guideline for Elemental Impurities. ICH, 2022.
6. Tchounwou PB, Yedjou CG, Patlolla AK, Sutton DJ. Heavy metal toxicity and the environment. EXS, 2012; 101: 133–164.
7. Järup L. Hazards of heavy metal contamination. Br Med Bull, 2003; 68: 167–182.
8. Satarug S, Garrett SH, Sens MA, Sens DA. Cadmium, environmental exposure, and health outcomes. Environ Health Perspect, 2010; 118: 182–190.
9. World Health Organization. WHO Good Practices for Herbal Medicines. Geneva: WHO.
10. Clarkson TW, Magos L. The toxicology of mercury and its chemical compounds. Crit Rev Toxicol, 2006; 36: 609–662.
11. Boss CB, Fredeen KJ. Concepts, Instrumentation and Techniques in Inductively Coupled Plasma Optical Emission Spectrometry. 3rd ed. PerkinElmer, 2004.
12. Alloway BJ, ed. Heavy Metals in Soils. 3rd ed. Dordrecht: Springer, 2013.
13. Clemens S, Ma JF. Toxic heavy metal and metalloid accumulation in crop plants and foods. Annu Rev Plant Biol, 2016; 67: 489–512.
14. World Health Organization. WHO Good Practices for Pharmaceutical Quality Control Laboratories. Geneva: WHO, 2024.
15. Shahid M, Dumat C, Khalid S, Niazi NK, Antunes PM. Cadmium bioavailability, uptake, toxicity and detoxification in soil-plant system. Rev Environ Contam Toxicol, 2017; 241: 73–137.
16. International Council for Harmonisation. ICH Q2(R2): Validation of Analytical Procedures. ICH, 2023.
17. World Health Organization. Quality Control Methods for Medicinal Plant Materials. Geneva: WHO, 1998.
18. Chen Y, et al. Progress in ICP-MS Analysis of Minerals and Heavy Metals in Traditional Medicine. Evid Based Complement Alternat Med, 2022.
19. He M, Niu X, Xing Y, Liang Y, Song H, Ding X, Huang Y. Research progress of the detection and analysis methods of heavy metals in plants. Front Plant Sci, 2024.
20. World Health Organization. WHO Good Practices for Pharmaceutical Quality Control Laboratories. WHO Technical Report Series 1052, Annex 4. Geneva: WHO, 2024.
21. Kabata-Pendias A. Trace Elements in Soils and Plants. 4th ed. Boca Raton: CRC Press, 2011.

22. International Council for Harmonisation. ICH Q9(R1): Quality Risk Management. ICH, 2023.
23. Gałuszka A, Migaszewski ZM, Namieśnik J. The 12 principles of green analytical chemistry and the SIGNIFICANCE mnemonic. TrAC Trends Anal Chem, 2013; 50: 78–84.
24. Yuan X, Chapman RL, Wu Z. Analytical methods for heavy metals in herbal medicines. Phytochem Anal, 2011; 22: 189–198. doi:10.1002/pca.1287.
25. Hughes MF. Arsenic toxicity and potential mechanisms of action. Toxicol Lett, 2002; 133: 1–16.
26. World Health Organization. WHO Guidelines on Good Agricultural and Collection Practices (GACP) for Medicinal Plants. Geneva: WHO, 2003.
27. Lux A, Martinka M, Vaculík M, White PJ. Root responses to cadmium in the rhizosphere. Plant Soil, 2011; 332: 1–19.
28. International Organization for Standardization. ISO 24153: Random sampling and randomization procedures. Geneva: ISO.